

siunitx – A comprehensive (SI) units package*

Joseph Wright[†]

Released 2022-04-25

Contents

I	siunitx-angle – Formatting angles	1
1	Formatting angles	1
1.1	Key-value options	1
II	siunitx-compound – Compound numbers and quantities	3
III	siunitx-locale – Localisation	5
IV	siunitx-number – Parsing and formatting numbers	6
1	Formatting numbers	6
1.1	Key-value options	8
V	siunitx-print – Printing material with font control	13
1	Printing quantities	13
1.1	Key-value options	14
VI	siunitx-quantity – Quantities	17
VII	siunitx-symbol – Symbol-related settings	18
VIII	siunitx-table – Formatting numbers in tables	19

*This file describes v3.1.0, last revised 2022-04-25.

[†]E-mail: joseph.wright@morningstar2.co.uk

1	Numbers in tables	19
1.1	Key-value options	19
IX	siunitx-unit – Parsing and formatting units	21
1	Formatting units	21
2	Defining symbolic units	23
3	Per-unit options	24
4	Units in (PDF) strings	24
5	Pre-defined symbolic unit components	24
5.1	Key-value options	27
X	siunitx-abbreviations – Abbreviations	30
XI	siunitx-binary – Binary units	33
XII	siunitx-command – Units as document command	34
1	Creating units as document commands	34
1.1	Key-value options	34
XIII	siunitx-emulation – Emulation	35
	Index	36

Part I

siunitx-angle – Formatting angles

1 Formatting angles

`\siunitx_angle:n`
`\siunitx_angle:nnn`

`\siunitx_angle:n {⟨angle⟩}`
`\siunitx_angle:nnn {⟨degrees⟩} {⟨minutes⟩} {⟨seconds⟩}`

Typeset the $\langle angle \rangle$ (which may be given as separate $\langle degree \rangle$, $\langle minute \rangle$ and $\langle second \rangle$ components). The $\langle angle \rangle$ (or components) may be given as expressions. The $\langle angle \rangle$ should be a number as understood by `\siunitx_format_number:nN`, with no uncertainty, exponent or imaginary part. The unit symbols for degrees, minutes and seconds are `\degree`, `\arcminute` and `\arcsecond`, respectively

1.1 Key-value options

The options defined by this submodule are available within the `l3keys siunitx` tree.

`angle-mode`

`angle-mode = ⟨choice⟩`

Selects how angles are formatted: a choice from the options `arc`, `decimal` and `input`. The option `arc` means that angles will always be typeset in arc (degree, minute, second) format, whilst `decimal` means that angles are typeset as a single decimal value. The `input` setting means that the input format (*i.e.* difference between `\siunitx_angle:n` and `\siunitx_angle:nnn`) is maintained. The standard setting is `input`.

`angle-symbol-degree`
`angle-symbol-minute`
`angle-symbol-second`

`angle-symbol-degree = ⟨symbol⟩`

Sets the symbol used for arc degrees, minutes or seconds, respectively.

`angle-symbol-over-decimal`

`angle-symbol-over-decimal = true|false`

Determines if the arc separator is printed over the decimal marker, a format used in astronomy. The standard setting is `false`.

`arc-separator`

`arc-separator = ⟨separator⟩`

Inserted between arc parts (degree, minute and second components). The standard setting is `\,`.

`fill-angle-degrees`

`fill-arc-degrees = true|false`

Determines whether a missing degrees part is zero-filled when printing an arc. The standard setting is `false`.

`fill-angle-minutes`

`fill-arc-minutes = true|false`

Determines whether a missing minutes part is zero-filled when printing an arc. The standard setting is `false`.

fill-angle-seconds**fill-arc-seconds = true|false**

Determines whether a missing seconds part is zero-filled when printing an arc. The standard setting is **false**.

number-angle-product**number-angle-product = $\langle separator \rangle$**

Inserted between the value of an angle and the unit (degree, minute or second component). The standard setting is $\backslash,$.

Part II

siunitx-compound – Compound numbers and quantities

<code>\siunitx_compound_number:n</code>	<code>\siunitx_compound_number:n {<entries>}</code>
---	---

Prints a set of numbers in the $\langle entries \rangle$, each of which should be given as a $\langle balanced text \rangle$. Unlike `\siunitx_number_list:nn`, this function may semantically take any form

<code>\siunitx_compound_quantity:nn</code>	<code>\siunitx_compound_quantity:nn {<entries>} {<unit>}</code>
--	---

Prints a set of quantities in the $\langle entries \rangle$, each of which should be given as a $\langle balanced text \rangle$. Unlike `\siunitx_quantity_list:nn`, this function may semantically take any form

<code>\siunitx_number_list:nn</code>	<code>\siunitx_number_list:nn {<entries>}</code>
--------------------------------------	--

Prints the list of numbers in the $\langle entries \rangle$, each of which should be given as a $\langle balanced text \rangle$.

<code>\siunitx_quantity_list:nn</code>	<code>\siunitx_quantity_list:nn {<entries>} {<unit>}</code>
--	---

Prints the list of quantities in the $\langle entries \rangle$, each of which should be given as a $\langle balanced text \rangle$.

<code>\siunitx_number_product:n</code>	<code>\siunitx_number_product:n {<entries>}</code>
--	--

Prints the series of numbers in the $\langle entries \rangle$, each of which should be given as a $\langle balanced text \rangle$.

<code>\siunitx_quantity_product:nn</code>	<code>\siunitx_number_product:n {<entries>} {<unit>}</code>
---	---

Prints the series of quantities in the $\langle entries \rangle$, each of which should be given as a $\langle balanced text \rangle$.

<code>\siunitx_number_range:nn</code>	<code>\siunitx_number_range:nn {<start>} {<end>}</code>
---------------------------------------	---

Prints the range of numbers from the $\langle start \rangle$ to the $\langle end \rangle$.

<code>\siunitx_quantity_range:nnn</code>	<code>\siunitx_number_range:nn {<start>} {<end>} {<unit>}</code>
--	--

Prints the range of quantities from the $\langle start \rangle$ to the $\langle end \rangle$.

<code>\l_siunitx_list_separator_pair_tl</code>
<code>\l_siunitx_list_separator_tl</code>
<code>\l_siunitx_list_separator_final_tl</code>

Separators for lists of numbers and quantities.

<u><u>\l_siunitx_range_phrase_tl</u></u>	Phrase (or similar) used between limits of a range.
<u><u>compound-exponents</u></u>	compound-exponents = combine combine-bracket individual
<u><u>compound-final-separator</u></u>	compound-final-separator = $\langle text \rangle$
<u><u>compound-pair-separator</u></u>	compound-pair-separator = $\langle text \rangle$
<u><u>compound-separator</u></u>	compound-separator = $\langle text \rangle$
<u><u>compound-separator-mode</u></u>	compound-separator-mode = number text
<u><u>compound-units</u></u>	compound-units = bracket repeat single
<u><u>list-exponents</u></u>	list-exponents = combine combine-bracket individual
<u><u>list-final-separator</u></u>	list-final-separator = $\langle text \rangle$
<u><u>list-pair-separator</u></u>	list-pair-separator = $\langle text \rangle$
<u><u>list-separator</u></u>	list-separator = $\langle text \rangle$
<u><u>list-units</u></u>	list-units = bracket repeat single
<u><u>product-exponents</u></u>	product-exponents = combine combine-bracket individual
<u><u>product-mode</u></u>	product-mode = phrase choice
<u><u>product-phrase</u></u>	product-phrase = $\langle text \rangle$
<u><u>product-symbol</u></u>	product-symbol = $\langle symbol \rangle$
<u><u>range-exponents</u></u>	range-exponents = combine combine-bracket individual
<u><u>range-phrase</u></u>	range-phrase = $\langle text \rangle$
<u><u>range-units</u></u>	range-units = bracket repeat single

Part III

siunitx-locale – Localisation

This submodule is concerned with localisation of `siunitx` output based on the locale. If the `translations` package is available, this is loaded here and used to provide various fixed strings for output.

locale

`locale = $\langle locale \rangle$`

Selects the $\langle locale \rangle$ used to apply standard settings for other keys, principally `exponent-product`, `inter-unit-product` and `output-decimal-marker`.

Part IV

siunitx-number – Parsing and formatting numbers

This submodule is dedicated to parsing and formatting numbers. A small number of L^AT_EX 2_ε math mode commands are assumed to be available as part of the formatted output. The sign commands `\mp`, `\pm`, `\ll`, `\le`, `\gg` and `\ge` are used to replace two-character input; `\pm` is also required for the output of uncertainties. The standard settings require `\times`. For the display of colored negative numbers, the command `\color` is assumed to be available. Where the latter may apply, numbers should be printed inside a group: note that T_EX grouping is not added *within* formatted numbers as they may need to be decomposed into parts (see `\siunitx_number_output:NN`). Such a color will be the *first* part of the result, meaning that a test for an initial `\color` and following brace group may be used to detect/remove/adjust this part.

1 Formatting numbers

```
\siunitx_number_parse:nN
\siunitx_number_parse:VN
```

```
\siunitx_number_parse:nN {<number>} <tl var>
```

Parses the *number* and stores the resulting internal representation in the *<tl var>*. The parsing is influenced by the various key–value settings for numerical input. The *<number>* should comprise a single real value, possibly with comparator, uncertainty and exponent parts. If the number is invalid, or if number parsing is disabled, the result will be an entirely empty *<tl var>*.

The structure of a valid number is:

$$\{ \langle \textit{comparator} \rangle \} \{ \langle \textit{sign} \rangle \} \{ \langle \textit{integer} \rangle \} \{ \langle \textit{decimal} \rangle \} \{ \langle \textit{uncertainty} \rangle \} \\ \{ \langle \textit{exponent sign} \rangle \} \{ \langle \textit{exponent} \rangle \}$$

where the two sign parts must be single tokens if present, and all other components must be given in braces. The number will have at least one digit for both the *<integer>* and *<exponent>* parts: these are required. The *<uncertainty>* part should either be blank or contain an *<identifier>* (as a brace group), followed by one or more data entries. Valid uncertainty *<identifiers>* currently are

- S** A single symmetrical uncertainty (*e.g.* a statistical standard uncertainty). The data item here is a single value representing the uncertainty in the least-significant digits
- A** A single unsymmetrical uncertainty. The data item here contains two brace groups, each using the same least-significant digit approach as the **S** type. The positive component is given first and the negative second, and neither has a sign.
- A combination of **S** and **A** entries, with one data item per entry. These are then iterated over to be output in order.

If a decimal marker should be explicitly recorded as present for a value with no decimal digits, the *<decimal>* part should contain `\empty`.

`\siunitx_number_process:NN`

`\siunitx_number_process:N` $\langle tl\ var1 \rangle$ $\langle tl\ var2 \rangle$

Applies a set of number processing operations to the $\langle internal\ number \rangle$ stored in the $\langle tl\ var1 \rangle$, viz. in order

1. Dropping uncertainty
2. Converting to scientific mode (or similar)
3. Rounding
4. Dropping zero decimal part
5. Forcing a minimum number of digits

with the result stored in $\langle tl\ var2 \rangle$.

`\siunitx_number_output:N` ☆

`\siunitx_number_output:N` $\langle number \rangle$

`\siunitx_number_output:n` ☆ `\siunitx_number_output:NN` $\langle number \rangle$ $\langle marker \rangle$

`\siunitx_number_output:NN` ☆

`\siunitx_number_output:nN` ☆

Formats the $\langle number \rangle$ (in the siunitx internal format), producing the result in a form suitable for typesetting in math mode. The details for the formatting are controlled by a number of key-value options. Note that *formatting* does not apply any manipulation (processing) to the number. This function is usable in an e- or x-type expansion, and further uncontrolled expansion is prevented by appropriate use of `\exp_not:n` internally.

In the NN version, the $\langle marker \rangle$ token is inserted at each possible alignment position in the output, viz.

- Between the comparator and the integer (*before* any sign for the integer)
- Between the sign and the first digit of the integer
- Both sides of the decimal marker
- Both sides of the separated uncertainty sign (*i.e.* after the decimal part and before any integer uncertainty part)
- Both sides of the decimal marker for a separated uncertainty
- Both sides of the multiplication symbol for the exponent part.

The n and nN version take a token list, which should be in the internal siunitx format.

`\siunitx_number_format:nN`

`\siunitx_number_format:nN` $\{\langle number \rangle\}$ $\langle tl\ var \rangle$

Carries out a combination of `\siunitx_number_parse:nN`, `\siunitx_number_process:NN` and `\siunitx_number_output:N` using x-type expansion to place the result in the $\langle tl\ var \rangle$. If `\l_siunitx_number_parse_bool` if false, the input is simply stored inside the $\langle tl\ var \rangle$ inside `\ensuremath`.

`\siunitx_number_adjust_exponent:Nn` ★ `\siunitx_number_adjust_exponent:Nn` $\langle number \rangle$ $\{\langle fp\ expr \rangle\}$

`\siunitx_number_adjust_exponent:nn` ★

Adjusts the exponent of the $\langle number \rangle$ (in internal format) by the $\langle fp\ expr \rangle$ and leaves the result in the input stream.

 $\backslash\text{siunitx_number_normalize_symbols:N}$ $\backslash\text{siunitx_number_normalize_symbols:N} \langle \text{tl var} \rangle$

Replaces all multi-token signs and comparators in the $\langle \text{tl var} \rangle$ with their single-token equivalents. Replaces any active hyphen tokens with non-active versions.

 $\backslash\text{siunitx_if_number_p:n}$ \star $\backslash\text{siunitx_if_number_token:NTF}$ $\{\langle \text{tokens} \rangle\}$
 $\backslash\text{siunitx_if_number:nTF}$ \star $\{\langle \text{true code} \rangle\} \{\langle \text{false code} \rangle\}$

Determines if the $\langle \text{tokens} \rangle$ form a valid number which can be fully parsed by `siunitx`.

 $\backslash\text{siunitx_if_number_token:NTF}$ $\backslash\text{siunitx_if_number_token:NTF} \{\langle \text{token} \rangle\}$
 $\{\langle \text{true code} \rangle\} \{\langle \text{false code} \rangle\}$

Determines if the $\langle \text{token} \rangle$ is valid in a number based on those tokens currently set up for detection in a number.

 $\backslash\text{l_siunitx_bracket_ambiguous_bool}$

A switch to control whether ambiguous numbers are bracketed: this can also be covered in quantity formatting by a setting there.

 $\backslash\text{l_siunitx_number_parse_bool}$

A switch to control whether any parsing is attempted for numbers.

 $\backslash\text{l_siunitx_number_comparator_tl}$
 $\backslash\text{l_siunitx_number_exponent_tl}$
 $\backslash\text{l_siunitx_number_sign_tl}$

The list of possible input comparators, exponent markers and signs.

 $\backslash\text{l_siunitx_number_input_decimal_tl}$
 $\backslash\text{l_siunitx_number_output_decimal_tl}$

The list of possible input decimal marker(s), and the output marker.

1.1 Key-value options

The options defined by this submodule are available within the `l3keys siunitx` tree.

`bracket-ambiguous-numbers` `bracket-ambiguous-numbers = true|false`

`bracket-negative-numbers` `bracket-negative-numbers = true|false`

`drop-exponent` `drop-exponent = true|false`

`drop-uncertainty` `drop-uncertainty = true|false`

`drop-zero-decimal` `drop-zero-decimal = true|false`

<u>evaluate-expression</u>	evaluate-expression = true false
<u>exponent-base</u>	exponent-base = $\langle base \rangle$
<u>exponent-mode</u>	exponent-mode = engineering fixed input scientific
<u>exponent-product</u>	exponent-product = $\langle symbol \rangle$
<u>expression</u>	expression = $\langle expression \rangle$
<u>fixed-exponent</u>	fixed-exponent = $\langle exponent \rangle$
<u>digit-group-size</u> <u>digit-group-first-size</u> <u>digit-group-other-size</u>	<p>digit-group-number = $\langle integer \rangle$</p> <p>Sets the size of the block (the number of digits) used when grouping digits. The option digit-group-first-size applies to the first grouping, <i>i.e.</i> immediately next to the decimal marker, while digit-group-other-size applies to all other groups. Both can be set using digit-group-size. The standard setting for both options is 3.</p>
<u>group-digits</u>	<p>group-digits = all decimal integer none</p> <p>Choice to specify whether digits in a number are grouped. The option none entirely disables this, while all means that both the integer and decimal parts are grouped. The settings integer and decimal activate grouping for the relevant part only. The standard setting is all.</p>
<u>group-minimum-digits</u>	<p>group-minimum-digits = $\langle value \rangle$</p> <p>The number of digits that must be present in a numerical part (integer or decimal) before digit grouping is attempted. The standard setting is 4.</p>
<u>group-separator</u>	<p>group-separator = $\langle symbol \rangle$</p> <p>Sets the symbol inserted between groups of digits. The standard setting is a thin space ($\backslash,$).</p>
<u>input-close-uncertainty</u>	input-close-uncertainty = $\langle tokens \rangle$
<u>input-comparators</u>	input-comparators = $\langle tokens \rangle$
<u>input-close-uncertainty</u>	input-close-uncertainty = $\langle tokens \rangle$
<u>input-decimal-markers</u>	input-decimal-markers = $\langle tokens \rangle$

<u>input-digits</u>	input-digits = $\langle tokens \rangle$
<u>input-exponent-markers</u>	input-exponent-markers = $\langle tokens \rangle$
<u>input-open-uncertainty</u>	input-open-uncertainty = $\langle tokens \rangle$
<u>input-signs</u>	input-signs = $\langle tokens \rangle$
<u>input-uncertainty-signs</u>	input-uncertainty-signs = $\langle tokens \rangle$
<u>minimum-decimal-digits</u>	minimum-decimal-digits = $\langle min \rangle$
<u>minimum-integer-digits</u>	minimum-integer-digits = $\langle min \rangle$
<u>negative-color</u>	negative-color = $\langle color \rangle$
<u>output-close-uncertainty</u>	output-close-uncertainty = $\langle symbol \rangle$
<u>output-decimal-marker</u>	output-decimal-marker = $\langle symbol \rangle$
<u>output-open-uncertainty</u>	output-open-uncertainty = $\langle symbol \rangle$
<u>parse-numbers</u>	parse-numbers = true false
<u>print-implicit-plus</u>	print-implicit-plus = true false
<u>print-unity-mantissa</u>	print-unity-mantissa = true false
<u>print-zero-exponent</u>	print-zero-exponent = true false
<u>print-zero-integer</u>	print-zero-integer = true false
<u>retain-explicit-plus</u>	retain-explicit-plus = true false
	Switch which determines if an explicit + is retained as a sign when parsing. The standard setting is false.

<u>retain-explicit-decimal-marker</u>	<code>retain-explicit-decimal-marker = true false</code>	Switch which determines if an explicit decimal marker is retained when parsing a number where there is no decimal part to a number (<i>i.e.</i> whether to differentiate 10 and 10.). The standard setting is false .
<u>retain-negative-zero</u>	<code>retain-negative-zero = true false</code>	Switch which determines if a negative sign is retained where the value of a parsed number is exactly zero. The standard setting is false .
<u>retain-zero-uncertainty</u>	<code>retain-zero-uncertainty = true false</code>	Switch which determines if an entirely zero uncertainty part is retained on parsing, or whether this is normalised to remove the uncertainty. The standard setting is false .
<u>round-half</u>	<code>round-half = even up</code>	Choice which determines how values of exactly half are rounded. The setting up means that the value is always rounded away from zero, whereas the setting even means that the value will be rounded to the closes even number. The standard setting is up .
<u>round-minimum</u>	<code>round-minimum = $\langle min \rangle$</code>	Literal which sets a minimum value below which rounded values will be replaced by this value and a > or <, as appropriate for the sign of the value. The standard setting is empty, <i>i.e.</i> there is no minimum.
<u>round-mode</u>	<code>round-mode = figures none places uncertainty</code>	Choice which specifies the rounding approach used for numbers. The choice figures means that values are rounding to the number of significant figures specified by round-precision . The setting places rounds to round-precision interpreted as a number of decimal places: this may be negative (rounding to an integer). The setting none disables rounding. The setting uncertainty first rounds the uncertainty to the number of significant figures specified by round-precision , then rounds the main value such that its accuracy is correctly specified by this updated uncertainty. The standard setting is none .
<u>round-pad</u>	<code>round-pad = true false</code>	Switch which specifies if values should be padded to the required number length when rounding to a number of decimal places. The standard setting is true .
<u>round-precision</u>	<code>round-precision = $\langle precision \rangle$</code>	Integer specifying the number of digits used as a target when rounding: this may be interpreted as decimal places or significant figures, depending on active round-mode . The standard setting is 2.
<u>round-zero-positive</u>	<code>round-zero-positive = true false</code>	Switch to control whether a value rounded to zero is regarded as a positive number if the input was negative. The standard setting is true .

<u>tight-spacing</u>	<code>tight-spacing = true false</code>
<u>uncertainty-descriptor-mode</u>	<code>uncertainty-descriptor = bracket bracket-separator separator subscript</code> <p>Selects how uncertainty descriptors are formatted: a choice from the options bracket, text and subscript. The option bracket wraps the descriptor in parenthesis, bracket-separator does the same but also includes a separator between the uncertainty and opening bracket, separator places the descriptor after the uncertainty and a separator, and subscript formats the descriptor as a subscript. The standard setting is bracket-separator.</p>
<u>uncertainty-descriptor-separator</u>	<code>uncertainty-descriptor-separator = \langleseparator\rangle</code> <p>Separator inserted between the uncertainty and descriptor when one is required by uncertainty-separator-mode. The standard setting is \backslash_{\perp}.</p>
<u>uncertainty-descriptors</u>	<code>uncertainty-descriptors = \langleclist\rangle</code> <p>Stores the list of descriptors used when there are multiple uncertainty components given. This is not used when there is only a single uncertainty component present. The standard setting is empty.</p>
<u>uncertainty-mode</u>	<code>uncertainty-mode = compact compact-marker full separate</code> <p>Switch to determine how single symmetrical uncertainties are formatted. When this is set to separate, the uncertainty is printed as an entirely separate number preceded by \backslash_{pm}. Other settings all place the uncertainty in parentheses directly attached to the main value. The standard setting of compact prints digits of uncertainty in the least-significant digits. It does <i>not</i> print a decimal marker if the uncertainty crosses the decimal. The setting full prints the full value of the uncertainty. The setting compact-marker is available to print in the compact style except where the uncertainty crosses the decimal, in which case the full style is used. The standard setting is compact.</p>
<u>uncertainty-separator</u>	<code>uncertainty-separator = \langleseparator\rangle</code> <p>Stores the separator used between the main value and uncertainty when using the compact or compact-marker style setting for uncertainty-mode.</p>
<u>zero-decimal-as-symbol</u>	<code>zero-decimal-as-symbol = true false</code> <p>Switch to determine if an entirely zero decimal part is replaced by a symbol. Does not apply if the decimal part is marked as entirely absent.</p>
<u>zero-symbol</u>	<code>zero-symbol = \langlesymbol\rangle</code> <p>Material printed when a zero numerical component is replaced by a symbol.</p>

Part V

siunitx-print – Printing material with font control

1 Printing quantities

This submodule is focussed on providing controlled printing for numbers and units. Key to this is control of font: conventions for printing quantities mean that the exact nature of the output is important. At the same time, this module provides flexibility for the user in terms of which aspects of the font are responsive to the surrounding general text. Printing material may also take place in text or math mode.

The printing routines assume that normal L^AT_EX 2_ε font selection commands are available, in particular `\bfseries`, `\mathrm`, `\mathversion`, `\fontfamily`, `\fontseries` and `\fontshape`, `\familydefault`, `\seriesdefault`, `\shapedefault` and `\selectfont`. It also requires the standard L^AT_EX 2_ε kernel commands `\ensuremath`, `\mbox`, `\textsubscript` and `\textsuperscript` for printing in text mode. The following packages are also required to provide the functionality detailed.

- `color`: support for color using `\textcolor`
- `textcomp`: `\textminus`, `\textpm`, `\texttimes` and `\textcenteredperiod` for printing in text mode
- `amstext`: the `\text` command for printing in text mode

For detection of math mode fonts, as well as `\mathrm`, the existence of `\symoperators` is assumed; other math font commands are not *required* to exist.

```
\siunitx_print_number:n  
\siunitx_print_number:(V|x)  
\siunitx_print_unit:n  
\siunitx_print_unit:(V|x)
```

```
\siunitx_print_number:n {<material>}  
\siunitx_print_unit:n {<material>}
```

Prints the *<material>* according to the prevailing settings for the submodule as applicable to the *<type>* of content (**number** or **unit**). The *<material>* should comprise normal L^AT_EX mark-up for numbers or units. In particular, units will typically use `\mathrm` to indicate material to be printed in the current upright roman font, and `^` and `_` will typically be used to indicate super- and subscripts, respectively. These elements will be correctly handled when printing for example using `\mathsf` in math mode, or using only text fonts.

```
\siunitx_print_match:n  
\siunitx_print_math:n  
\siunitx_print_text:n
```

```
\siunitx_print_match:n {<material>}  
\siunitx_print_math:n {<material>}  
\siunitx_print_text:n {<material>}
```

Prints the *<material>* as described for `\siunitx_print_...:n` but with a fixed text or math mode output. The printing does *not* set color (which is managed on a **unit/number** basis), but otherwise sets the font as described above. The **match** function uses either the prevailing math or text mode.

1.1 Key-value options

The options defined by this submodule are available within the l3keys `siunitx` tree.

<hr/> <hr/> <code>color</code>	<code>color = <color></code> Color to apply to printed output: the latter should be a named color defined for use with <code>\textcolor</code> . The standard setting is empty (no color).
<hr/> <hr/> <code>mode</code>	<code>mode = match math text</code> Selects which mode (math or text) the output is printed in: a choice from the options <code>match</code> , <code>math</code> or <code>text</code> . The option <code>match</code> matches the mode prevailing at the point <code>\siunitx_print_...:n</code> is called. The <code>math</code> and <code>text</code> options choose the relevant T _E X mode for printing. The standard setting is <code>math</code> .
<hr/> <hr/> <code>number-color</code>	<code>number-color = <color></code> Color to apply to numbers in output: the latter should be a named color defined for use with <code>\textcolor</code> . The standard setting is empty (no color).
<hr/> <hr/> <code>number-mode</code>	<code>number-mode = match math text</code> Selects which mode (math or text) the numbers are printed in: a choice from the options <code>match</code> , <code>math</code> or <code>text</code> . The option <code>match</code> matches the mode prevailing at the point <code>\siunitx_prin_number:n</code> is called. The <code>math</code> and <code>text</code> options choose the relevant T _E X mode for printing. The standard setting is <code>math</code> .
<hr/> <hr/> <code>propagate-math-font</code>	<code>propagate-math-font = true false</code> Switch to determine if the currently-active math font is applied within printed output. This is relevant only when <code>\siunitx_print_...:n</code> is called from within math mode: in text mode there is not active math font. When not active, math mode material will be typeset using standard math mode fonts without any changes being made to the supplied argument. The standard setting is <code>false</code> .
<hr/> <hr/> <code>reset-math-version</code>	<code>reset-math-version = true false</code> Switch to determine whether the active <code>\mathversion</code> is reset to <code>normal</code> when printing in math mode. Note that math version is typically used to select <code>\boldmath</code> , though it is also be used by <i>e.g.</i> <code>sansmath</code> . The standard setting is <code>true</code> .
<hr/> <hr/> <code>reset-text-family</code>	<code>reset-text-family = true false</code> Switch to determine whether the active text family is reset to <code>\rmfamily</code> when printing in text mode. The standard setting is <code>true</code> .
<hr/> <hr/> <code>reset-text-series</code>	<code>reset-text-series = true false</code> Switch to determine whether the active text series is reset to <code>\mdseries</code> when printing in text mode. The standard setting is <code>true</code> .
<hr/> <hr/> <code>reset-text-shape</code>	<code>reset-text-shape = true false</code> Switch to determine whether the active text shape is reset to <code>\upshape</code> when printing in text mode. The standard setting is <code>true</code> .

<hr/> <hr/> text-family-to-math	text-family-to-math = true false
	Switch to determine if the family of the current text font should be applied (where possible) to printing in math mode. The standard setting is false .
<hr/> <hr/> text-font-command	text-font-command = $\langle cmd \rangle$
	Command applied to text during output, inserted after any reset of font set-up. This can therefore be used to apply non-standard font set up when printing in text mode. The standard setting is empty.
<hr/> <hr/> text-series-to-math	text-series-to-math = true false
	Switch to determine if the weight of the current text font should be applied (where possible) to printing in math mode. This is achieved by setting the <code>\mathversion</code> , and so will override <code>reset-math-version</code> . The mappings between text and math weight are set . The standard setting is false .
<hr/> <hr/> text-subscript-command	text-subscript-command = $\langle cmd \rangle$
text-superscript-command	text-superscript-command = $\langle cmd \rangle$
	Sets the command used when printing material in sub- or superscript positions in text mode. The standard settings are <code>\textsubscript</code> and <code>\textsuperscript</code> , respectively.
<hr/> <hr/> unit-color	unit-color = $\langle color \rangle$
	Color to apply to units in output: the latter should be a named color defined for use with <code>\textcolor</code> . The standard setting is empty (no color).
<hr/> <hr/> unit-mode	unit-mode = match math text
	Selects which mode (math or text) units are printed in: a choice from the options match , math or text . The option match matches the mode prevailing at the point <code>\siunitx-print_...:n</code> is called. The math and text options choose the relevant T _E X mode for printing. The standard setting is math .

series-version-mapping

`series-version-mapping / $\langle weight \rangle = \langle version \rangle$`

Defines how `siunitx` maps from text font weight to math font version. The pre-defined weights are those used as-standard by `autoinst`:

- `ul`
- `el`
- `l`
- `sl`
- `m`
- `sb`
- `b`
- `eb`
- `ub`

As standard, the `m` weight maps to `normal` math version whilst all of the `b` weights map to `bold` and all of the `l` weights map to `light`.

Part VI

siunitx-quantity – Quantities

This submodule is focussed on providing controlled printing for quantities: the combination of a number and a unit. It largely builds on the submodules `siunitx-number` and `siunitx-unit`. A small number of adjustments are made to standard set up in the latter to reflect additional functionality added here.

<code>\siunitx_quantity:nn</code>	<code>\siunitx_quantity:nn {<number>} {<unit>}</code>
-----------------------------------	---

Parses the `<number>` and the `<unit>` as detailed for `\siunitx_number_parse:nN` and `\siunitx_unit_format:nN`, then prints the results using `\siunitx_print_unit:n`.

<code>\siunitx_quantity_print:nn</code>	<code>\siunitx_quantity_print:nn {<number>} {<unit>}</code>
<code>\siunitx_quantity_print:(nV VV xV)</code>	

A low-level function which prints the quantity directly: there is no processing applied to either the `<number>` or `<unit>`. The two parts are printed using `\siunitx_print_unit:n` and appropriate spacing and break-prevention is applied.

<code>allow-quantity-breaks</code>	<code>allow-quantity-breaks = true false</code>
------------------------------------	---

Specifies whether breaks are permitted between units. The standard setting is `false`.

<code>prefix-mode</code>	<code>prefix-mode = combine-exponent extract-exponent input</code>
--------------------------	--

Selects the method used for producing prefixes: a choice from the options `combine-exponent`, `extract-exponent` and `input`. The option `combine-exponent` combines any exponent from the number with the prefix of the first unit, and prints the updated prefix. The option `extract-exponent` removes all prefixes from the unit, and combines them with the exponent of number. The option `input` prints prefixes and exponent as given in the source. The standard setting is `input`.

<code>quantity-product</code>	<code>quantity-product = <tokens></code>
-------------------------------	--

The product marker used between a number and the unit. The standard setting is `\,`.

<code>separate-uncertainty-units</code>	<code>separate-uncertainty-units = bracket repeat single</code>
---	---

Specifies how units are applied when a separated uncertainty is present: a choice from `bracket`, `repeat` and `single`. The option `bracket` places brackets around the number, with the unit given after these. The option `repeat` means that the unit is printed with the main value and with the uncertainty. When `single` is set, the unit is printed only once and no brackets are applied. The standard setting is `bracket`.

Part VII

siunitx-symbol – Symbol-related settings

Part VIII

siunitx-table – Formatting numbers in tables

1 Numbers in tables

This submodule is concerned with formatting numbers in table cells or similar fixed-width contexts. The main function, `\siunitx_cell_begin:w`, is designed to work with the normal $\text{\LaTeX} 2_{\epsilon}$ tabular cell construct featuring `\ignorespaces`. Therefore, if used outside of a $\text{\LaTeX} 2_{\epsilon}$ tabular, it is necessary to provide this token.

<code>\siunitx_cell_begin:w</code>	<code>\siunitx_cell_begin:w <preamble> \ignorespaces</code>
<code>\siunitx_cell_end:</code>	<code><content></code> <code>\siunitx_cell_end:</code>

Collects the `<preamble>` and `<content>` tokens, and determines if it is text or a number (as parsed by `\siunitx_number_parse:nN`). It produces output of a fixed width suitable for alignment in a table, although it is not *required* that the code is used within a cell. Note that `\ignorespaces` must occur in the “cell”: it marks the end of the \TeX `\halign` template.

1.1 Key-value options

The options defined by this submodule are available within the `l3keys siunitx` tree.

<code>table-align-comparator</code>	<code>table-align-comparator = true false</code>
-------------------------------------	--

Switch which determines whether alignment of comparators is attempted within table cells. The standard setting is `true`.

<code>table-align-exponent</code>	<code>table-align-exponent = true false</code>
-----------------------------------	--

Switch which determines whether alignment of exponents is attempted within table cells. The standard setting is `true`.

<code>table-align-text-after</code>	<code>table-align-text-after = true false</code>
-------------------------------------	--

Switch which determines whether alignment of text falling after a number is attempted within table cells. The standard setting is `true`.

<code>table-align-text-before</code>	<code>table-align-text-before = true false</code>
--------------------------------------	---

Switch which determines whether alignment of text falling before a number is attempted within table cells. The standard setting is `true`.

<code>table-align-uncertainty</code>	<code>table-align-uncertainty = true false</code>
--------------------------------------	---

Switch which determines whether alignment of separated uncertainty values is attempted within table cells. The standard setting is `true`.

<u>table-alignment</u>	<p><code>table-alignment = center left right</code></p> <p>Selects the alignment of all tabular content with the margins of the table cell (or other boundary). See also <code>table-number-alignment</code> and <code>table-text-alignment</code>. The standard setting is <code>center</code>.</p>
<u>table-alignment-mode</u>	<p><code>table-alignment-mode = format marker none</code></p> <p>Selects the method used to align numbers with the desired position in the cell (set by <code>table-alignment</code>). When set to <code>format</code>, a dedicated amount of space is calculated from the <code>table-format</code>. When <code>marker</code> is selected, alignment is carried out symmetrically around the decimal marker. Finally, <code>none</code> switches off all alignment: numbers are parsed and formatted but with no attempt at placement within the cell. The standard setting is <code>marker</code>.</p>
<u>table-auto-round</u>	<p><code>table-auto-round = true false</code></p> <p>Switch which determines whether numbers are rounded to fit within the <code>table-format</code> specification (if possible). The standard setting is <code>false</code>.</p>
<u>table-column-width</u>	<p><code>table-column-width = <width></code></p> <p>Sets the width of the table column used for numbers. This is only used when <code>table-fixed-width</code> is <code>true</code>.</p>
<u>table-fixed-width</u>	<p><code>table-fixed-width = true false</code></p> <p>Switch which determines whether a fixed-width column is used for numbers in tables. When <code>true</code>, the width is taken from <code>table-column-width</code>. The standard setting is <code>false</code>.</p>
<u>table-format</u>	<p><code>table-format = <format></code></p> <p>Describes the amount of space that should be reserved when <code>table-alignment-mode</code> is set to <code>format</code>. The <code><format></code> takes the same general form as input for a table cell, with the numerical parts describing how many digits to reserve space for. For example, <code>1.2e3</code> would allow space for one digit in the integer part, two in the decimal part and three in the exponent part. Signs can be allowed for using any valid input sign, so for example <code>+1.2 \pm 1.2</code> would allow for a sign, a number with one integer and two decimal digits and an uncertainty of the same size.</p>
<u>table-number-alignment</u>	<p><code>table-number-alignment = center left right</code></p> <p>Selects the alignment of numerical content with the margins of the table cell (or other boundary). See also <code>table-alignment</code> and <code>table-text-alignment</code>. The standard setting is <code>center</code>.</p>
<u>table-text-alignment</u>	<p><code>table-text-alignment = center left none right</code></p> <p>Selects the alignment of non-numerical content with the margins of the table cell (or other boundary). See also <code>table-alignment</code> and <code>table-number-alignment</code>. Notice the additional support for <code>none</code> here. The standard setting is <code>center</code>.</p>

Part IX

siunitx-unit – Parsing and formatting units

This submodule is dedicated to formatting physical units. The main function, `\siunitx-unit_format:nN`, takes user input specifying physical units and converts it into a formatted token list suitable for typesetting in math mode. While the formatter will deal correctly with “literal” user input, the key strength of the module is providing a method to describe physical units in a “symbolic” manner. The output format of these symbolic units can then be controlled by a number of key–value options made available by the module.

A small number of L^AT_EX 2_ε math mode commands are assumed to be available as part of the formatted output. The `\mathchoice` command (normally the T_EX primitive) is needed when using different settings for inline and display `per-mode`. The commands `\frac`, `\mathrm`, `\mbox`, `_` and `\,` are used by the standard module settings. For the display of colored (highlighted) and cancelled units, the commands `\textcolor` and `\cancel` are assumed to be available.

1 Formatting units

`\siunitx-unit_format:nN``\siunitx-unit_format:nN {<units>} <tl var>`

This function converts the input `<units>` into a processed `<tl var>` which can then be inserted in math mode to typeset the material. Where the `<units>` are given in symbolic form, described elsewhere, this formatting process takes place in two stages: the `<units>` are parsed into a structured form before the generation of the appropriate output form based on the active settings. When the `<units>` are given as literals, processing is minimal: the characters `.` and `~` are converted to unit products (boundaries). In both cases, the result is a series of tokens intended to be typeset in math mode with appropriate choice of font for typesetting of the textual parts.

For example,

```
\siunitx-unit_format:nN { \kilo \metre \per \second } \l_tmpa_tl
```

will, with standard settings, result in `\l_tmpa_tl` being set to

```
\mathrm{km}\,,\mathrm{s}^{-1}
```

<code>\siunitx_unit_format_extract_prefixes:nnN</code>	<code>\siunitx_unit_format_extract_prefixes:nnN {<units>} <tl var> <fp var></code>
--	--

This function formats the $\langle units \rangle$ in the same way as described for `\siunitx_unit_format:nN`. When the input is given in symbolic form, any decimal unit prefixes will be extracted and the overall power of ten that these represent will be stored in the $\langle fp var \rangle$.

For example,

```
\siunitx_unit_format_extract_prefixes:nnN { \kilo \metre \per \second }
\l_tmpa_tl \l_tmpa_fp
```

will, with standard settings, result in `\l_tmpa_tl` being set to

```
\mathrm{m}\,,\mathrm{s}^{-1}
```

with `\l_tmpa_fp` taking value 3. Note that the latter is a floating point variable: it is possible for non-integer values to be obtained here.

<code>\siunitx_unit_format_combine_exponent:nnN</code>	<code>\siunitx_unit_format_combine_exponent:nnN {<units>} <exponent> <tl var></code>
--	--

This function formats the $\langle units \rangle$ in the same way as described for `\siunitx_unit_format:nN`. The $\langle exponent \rangle$ is combined with any prefix for the *first* unit of the $\langle units \rangle$, and an updated prefix is introduced.

For example,

```
\siunitx_unit_format_combine_exponent:nnN { \metre \per \second }
{ 3 } \l_tmpa_tl
```

will, with standard settings, result in `\l_tmpa_tl` being set to

```
\mathrm{km}\,,\mathrm{s}^{-1}
```

<code>\siunitx_unit_format_multiply:nnN</code> <code>\siunitx_unit_format_multiply_extract_prefixes:nnNN</code> <code>\siunitx_unit_format_multiply_combine_exponent:nnnN</code>	<code>\siunitx_unit_format_multiply:nnN {<units>} <factor> <tl var></code> <code>\siunitx_unit_format_multiply_extract_prefixes:nnNN {<units>} <factor> <tl var> <fp var></code> <code>\siunitx_unit_format_multiply_combine_exponent:nnnN {<units>} <factor> <exponent> <tl var></code>
--	--

These function formats the $\langle units \rangle$ in the same way as described for `\siunitx_unit_format:nN`. The units are multiplied by the $\langle factor \rangle$, and further processing takes place as previously described.

For example,

```
\siunitx_unit_format_multiply:nnN { \metre \per \second }
{ 3 } \l_tmpa_tl
```

will, with standard settings, result in `\l_tmpa_tl` being set to

```
\mathrm{km}^3\,,\mathrm{s}^{-3}
```


2 Defining symbolic units

<code>\siunitx_declare_prefix:Nnn</code>	<code>\siunitx_declare_prefix:Nnn <prefix> {<power>} {<symbol>}</code>
<code>\siunitx_declare_prefix:Nnx</code>	

Defines a symbolic $\langle prefix \rangle$ (which should be a control sequence such as `\kilo`) to be converted by the parser to the $\langle symbol \rangle$. The latter should consist of literal content (e.g. `k`). In literal mode the $\langle symbol \rangle$ will be typeset directly. The prefix should represent an integer $\langle power \rangle$ of 10, and this information may be used to convert from one or more $\langle prefix \rangle$ symbols to an overall power applying to a unit. See also `\siunitx_declare_prefix:Nn`.

<code>\siunitx_declare_prefix:Nn</code>	<code>\siunitx_declare_prefix:Nn <prefix> {<symbol>}</code>
---	---

Defines a symbolic $\langle prefix \rangle$ (which should be a control sequence such as `\kilo`) to be converted by the parser to the $\langle symbol \rangle$. The latter should consist of literal content (e.g. `k`). In literal mode the $\langle symbol \rangle$ will be typeset directly. In contrast to `\siunitx_declare_prefix:Nnn`, there is no assumption about the mathematical nature of the $\langle prefix \rangle$, i.e. the prefix may represent a power of any base. As a result, no conversion of the $\langle prefix \rangle$ to a numerical power will be possible.

<code>\siunitx_declare_power:NNn</code>	<code>\siunitx_declare_power:NNn <pre-power> <post-power> {<value>}</code>
---	--

Defines *two* symbolic $\langle powers \rangle$ (which should be control sequences such as `\squared`) to be converted by the parser to the $\langle value \rangle$. The latter should be an integer or floating point number in the format defined for `l3fp`. Powers may precede a unit or be give after it: both forms are declared at once, as indicated by the argument naming. In literal mode, the $\langle value \rangle$ will be applied as a superscript to either the next token in the input (for the $\langle pre-power \rangle$) or appended to the previously-typeset material (for the $\langle post-power \rangle$).

<code>\siunitx_declare_qualifier:Nn</code>	<code>\siunitx_declare_qualifier:Nn <qualifier> {<meaning>}</code>
--	--

Defines a symbolic $\langle qualifier \rangle$ (which should be a control sequence such as `\catalyst`) to be converted by the parser to the $\langle meaning \rangle$. The latter should consist of literal content (e.g. `cat`). In literal mode the $\langle meaning \rangle$ will be typeset following a space after the unit to which it applies.

<code>\siunitx_declare_unit:Nn</code>	<code>\siunitx_declare_unit:Nn <unit> {<meaning>}</code>
<code>\siunitx_declare_unit:Nx</code>	<code>\siunitx_declare_unit:Nnn <unit> {<meaning>} {<options>}</code>
<code>\siunitx_declare_unit:Nnn</code>	
<code>\siunitx_declare_unit:Nxn</code>	

Defines a symbolic $\langle unit \rangle$ (which should be a control sequence such as `\kilogram`) to be converted by the parser to the $\langle meaning \rangle$. The latter may consist of literal content (e.g. `kg`), other symbolic unit commands (e.g. `\kilo\gram`) or a mixture of the two. In literal mode the $\langle meaning \rangle$ will be typeset directly. The version taking an $\langle options \rangle$ argument may be used to support per-unit options: these are applied at the top level or using `\siunitx_unit_options_apply:n`.

<code>\l_siunitx_unit_font_tl</code>	The font function which is applied to the text of units when constructing formatted units: set by <code>font-command</code> .
--------------------------------------	---

`\l_siunitx_unit_fraction_tl`

The fraction function which is applied when constructing fractional units: set by `fraction-command`.

`\l_siunitx_unit_symbolic_seq`

This sequence contains all of the symbolic names defined: these will be in the form of control sequences such as `\kilogram`. The order of the sequence is unimportant. This includes prefixes and powers as well as units themselves.

`\l_siunitx_unit_seq`

This sequence contains all of the symbolic *unit* names defined: these will be in the form of control sequences such as `\kilogram`. In contrast to `\l_siunitx_unit_symbolic_seq`, it *only* holds units themselves

3 Per-unit options

`\siunitx_unit_options_apply:n` `\siunitx_unit_options_apply:n` $\langle unit(s) \rangle$

Applies any unit-specific options set up using `\siunitx_declare_unit:Nnn`. This allows their use outside of unit formatting, for example to influence spacing in quantities. The options are applied only once at a given group level, which allows for user over-ride *via* `\keys_set:nn { siunitx } { ... }`.

4 Units in (PDF) strings

`\siunitx_unit_pdfstring_context:` `\group_begin:`
 `\siunitx_unit_pdfstring_context:`
 $\langle Expansion\ context \rangle$ $\langle units \rangle$
 `\group_end:`

Sets symbol unit macros to generate text directly. This is needed in expansion contexts where units must be converted to simple text. This function is itself not expandable, so must be used within a surrounding group as shown in the example.

5 Pre-defined symbolic unit components

The unit parser is defined to recognise a number of pre-defined units, prefixes and powers, and also interpret a small selection of “generic” symbolic parts.

Broadly, the pre-defined units are those defined by the BIPM in the documentation for the *International System of Units* (SI) [1]. As far as possible, the names given to the command names for units are those used by the BIPM, omitting spaces and using only ASCII characters. The standard symbols are also taken from the same documentation. In the following documentation, the order of the description of units broadly follows the SI Brochure.

<code>\kilogram</code>	The base units as defined in the SI Brochure [2]. Notice that <code>\meter</code> is defined as an alias for <code>\metre</code> as the former spelling is common in the US (although the latter is the official spelling).
<code>\metre</code>	
<code>\meter</code>	
<code>\mole</code>	
<code>\kelvin</code>	
<code>\candela</code>	
<code>\second</code>	
<code>\ampere</code>	

<code>\gram</code>	The base unit <code>\kilogram</code> is defined using an SI prefix: as such the (derived) unit <code>\gram</code> is required by the module to correctly produce output for the <code>\kilogram</code> .
--------------------	--

<code>\yocto</code>	Prefixes, all of which are integer powers of 10: the powers are stored internally by the module and can be used for conversion from prefixes to their numerical equivalent. These prefixes are documented in Section 3.1 of the SI Brochure.
<code>\zepto</code>	
<code>\atto</code>	
<code>\femto</code>	
<code>\pico</code>	
<code>\nano</code>	
<code>\micro</code>	
<code>\milli</code>	
<code>\centi</code>	
<code>\deci</code>	
<code>\deca</code>	
<code>\deka</code>	
<code>\hecto</code>	
<code>\kilo</code>	
<code>\mega</code>	
<code>\giga</code>	
<code>\tera</code>	
<code>\peta</code>	
<code>\exa</code>	
<code>\zetta</code>	
<code>\yotta</code>	

<hr/>	
<code>\becquerel</code>	The defined SI units with defined names and symbols, as given in Table 4 of the SI Brochure. Notice that the names of the units are lower case with the exception of <code>\degreeCelsius</code> , and that this unit name includes “degree”.
<code>\degreeCelsius</code>	
<code>\coulomb</code>	
<code>\farad</code>	
<code>\gray</code>	
<code>\hertz</code>	
<code>\henry</code>	
<code>\joule</code>	
<code>\katal</code>	
<code>\lumen</code>	
<code>\lux</code>	
<code>\newton</code>	
<code>\ohm</code>	
<code>\pascal</code>	
<code>\radian</code>	
<code>\siemens</code>	
<code>\sievert</code>	
<code>\steradian</code>	
<code>\tesla</code>	
<code>\volt</code>	
<code>\watt</code>	
<code>\weber</code>	
<hr/>	

<hr/>	
<code>\astronomicalunit</code>	Units accepted for use with the SI: here <code>\minute</code> is a unit of time not of plane angle. These units are taken from Table 8 of the SI Brochure.
<code>\bel</code>	
<code>\dalton</code>	For the unit <code>\litre</code> , both <code>l</code> and <code>L</code> are listed as acceptable symbols: the latter is the standard setting of the module. The alternative spelling <code>\liter</code> is also given for this unit for US users (as with <code>\metre</code> , the official spelling is “re”).
<code>\day</code>	
<code>\decibel</code>	
<code>\electronvolt</code>	
<code>\hectare</code>	
<code>\hour</code>	
<code>\litre</code>	
<code>\liter</code>	
<code>\neper</code>	
<code>\minute</code>	
<code>\tonne</code>	
<hr/>	

<hr/>	
<code>\arcminute</code>	Units for plane angles accepted for use with the SI: to avoid a clash with units for time, here <code>\arcminute</code> and <code>\arcsecond</code> are used in place of <code>\minute</code> and <code>\second</code> . These units are taken from Table 8 of the SI Brochure.
<code>\arcsecond</code>	
<code>\degree</code>	
<hr/>	

<hr/>	
<code>\percent</code>	The mathematical concept of percent, usable with the SI as detailed in Section 5.4.7 of the SI Brochure.
<hr/>	

<hr/>	
<code>\square</code>	<code>\square</code> <i><prefix></i> <i><unit></i>
<code>\cubic</code>	<code>\cubic</code> <i><prefix></i> <i><unit></i>
<hr/>	
	Pre-defined unit powers which apply to the next <i><prefix>/<unit></i> combination.

<hr/> \squared	$\langle prefix \rangle \langle unit \rangle \text{\squared}$
<hr/> \cubed	$\langle prefix \rangle \langle unit \rangle \text{\cubed}$
	Pre-defined unit powers which apply to the preceding $\langle prefix \rangle / \langle unit \rangle$ combination.
<hr/> \per	$\text{\per} \langle prefix \rangle \langle unit \rangle \langle power \rangle$
	Indicates that the next $\langle prefix \rangle / \langle unit \rangle / \langle power \rangle$ combination is reciprocal, <i>i.e.</i> raises it to the power -1 . This symbolic representation may be applied in addition to a \power , and will work correctly if the \power itself is negative. In literal mode \per will print a slash (“/”).
<hr/> \cancel	$\text{\cancel} \langle prefix \rangle \langle unit \rangle \langle power \rangle$
	Indicates that the next $\langle prefix \rangle / \langle unit \rangle / \langle power \rangle$ combination should be “cancelled out”. In the parsed output, the entire unit combination will be given as the argument to a function \cancel , which is assumed to be available at a higher level. In literal mode, the same higher-level \cancel will be applied to the next token. It is the responsibility of the calling code to provide an appropriate definition for \cancel outside of the scope of the unit parser.
<hr/> \highlight	$\text{\highlight} \{ \langle color \rangle \} \langle prefix \rangle \langle unit \rangle \langle power \rangle$
	Indicates that the next $\langle prefix \rangle / \langle unit \rangle / \langle power \rangle$ combination should be highlighted in the specified $\langle color \rangle$. In the parsed output, the entire unit combination will be given as the argument to a function \textcolor , which is assumed to be available at a higher level. In literal mode, the same higher-level \textcolor will be applied to the next token. It is the responsibility of the calling code to provide an appropriate definition for \textcolor outside of the scope of the unit parser.
<hr/> \of	$\langle prefix \rangle \langle unit \rangle \langle power \rangle \text{\of} \{ \langle qualifier \rangle \}$
	Indicates that the $\langle qualifier \rangle$ applies to the current $\langle prefix \rangle / \langle unit \rangle / \langle power \rangle$ combination. In parsed mode, the display of the result will depend upon module options. In literal mode, the $\langle qualifier \rangle$ will be printed in parentheses following the preceding $\langle unit \rangle$ and a full-width space.
<hr/> \raiseto	$\text{\raiseto} \{ \langle power \rangle \} \langle prefix \rangle \langle unit \rangle$
<hr/> \tothe	$\langle prefix \rangle \langle unit \rangle \text{\tothe} \{ \langle power \rangle \}$
	Indicates that the $\langle power \rangle$ applies to the current $\langle prefix \rangle / \langle unit \rangle$ combination. As shown, \raiseto applies to the next $\langle unit \rangle$ whereas \tothe applies to the preceding unit. In literal mode the \power will be printed as a superscript attached to the next token (\raiseto) or preceding token (\tothe) as appropriate.

5.1 Key-value options

The options defined by this submodule are available within the l3keys **siunitx** tree.

<hr/> bracket-unit-denominator	bracket-unit-denominator = true false
	Switch to determine whether brackets are added to the denominator part of a unit when printed using inline fractional form (with per-mode as repeated-symbol or symbol). The standard setting is true .

<hr/> extract-mass-in-kilograms <hr/>	extract-mass-in-kilograms = <code>true false</code> Determines whether prefix extraction treats kilograms as a base unit; when set <code>false</code> , grams are used. The standard setting is <code>true</code> .
<hr/> forbid-literal-units <hr/>	forbid-literal-units = <code>true false</code> Switch which determines if literal units are allowed when parsing is active; does not apply when <code>parse-units</code> is <code>false</code> .
<hr/> fraction-command <hr/>	fraction-command = $\langle command \rangle$ Command used to create fractional output when <code>per-mode</code> is set to <code>fraction</code> . The standard setting is <code>\frac</code> .
<hr/> inter-unit-product <hr/>	inter-unit-product = $\langle separator \rangle$ Inserted between unit combinations in parsed mode, and used to replace <code>.</code> and <code>~</code> in literal mode. The standard setting is <code>\,</code> .
<hr/> parse-units <hr/>	parse-units = <code>true false</code> Determines whether parsing of unit symbols is attempted or literal mode is used directly. The standard setting is <code>true</code> .
<hr/> per-mode inline-per-mode display-per-mode <hr/>	per-mode = <code>fraction power power-positive-first repeated-symbol single-symbol symbol</code> Selects how the negative powers (<code>\per</code>) are formatted: a choice from the options <code>fraction</code> , <code>power</code> , <code>power-positive-first</code> , <code>repeated-symbol</code> , <code>single-symbol</code> and <code>symbol</code> . The option <code>fraction</code> generates fractional output when appropriate using the command specified by the <code>fraction-command</code> option. The setting <code>power</code> uses reciprocal powers leaving the units in the order of input, while <code>power-positive-first</code> uses the same display format but sorts units such that the positive powers come before negative ones. The <code>symbol</code> setting uses a symbol (specified by <code>per-symbol</code>) between positive and negative powers, while <code>repeated-symbol</code> uses the same symbol but places it before <i>every</i> unit with a negative power (this is mathematically “wrong” but often seen in real work). The option <code>single-symbol</code> will use a symbol if exactly one is required (<i>i.e.</i> with a single negative power), and will otherwise use powers. The standard setting is <code>power</code> . The <code>inline-...</code> and <code>display-...</code> settings take the same options and work in exactly the same way, but are restricted in where they apply. The <code>display</code> version only applies in display math contexts, and the <code>inline</code> version applies in all others.
<hr/> per-symbol <hr/>	per-symbol = $\langle symbol \rangle$ Specifies the symbol to be used to denote negative powers when the option <code>per-mode</code> is set to <code>repeated-symbol</code> or <code>symbol</code> . The standard setting is <code>/</code> .
<hr/> per-symbol-script-correction <hr/>	per-symbol-script-correction = $\langle insert \rangle$ Specifies the tokens used to correct spacing when the symbol set by <code>per-symbol</code> is immediately preceded by a superscript power. The standard setting is <code>\!</code> .

<hr/> <hr/> power-half-as-sqrt	power-half-as-sqrt = true false Used to determine whether a power of exactly half is converted to <code>\sqrt</code> in the output. The standard setting is <code>false</code>
<hr/> <hr/> qualifier-mode	qualifier-mode = bracket combine phrase subscript Selects how qualifiers are formatted: a choice from the options <code>bracket</code> , <code>combine</code> , <code>phrase</code> and <code>subscript</code> . The option <code>bracket</code> wraps the qualifier in parenthesis, <code>combine</code> joins the qualifier with the unit directly, <code>phrase</code> joins the material using <code>qualifier-phrase</code> as a link, and <code>subscript</code> formats the qualifier as a subscript. The standard setting is <code>subscript</code> .
<hr/> <hr/> qualifier-phrase	qualifier-phrase = $\langle phrase \rangle$ Defines the $\langle phrase \rangle$ used when <code>qualifier-mode</code> is set to <code>phrase</code> .
<hr/> <hr/> sticky-per	sticky-per = true false Used to determine whether <code>\per</code> should be applied one a unit-by-unit basis (when <code>false</code>) or should apply to all following units (when <code>true</code>). The latter mode is somewhat akin conceptually to the <code>TeX \over</code> primitive. The standard setting is <code>false</code> .
<hr/> <hr/> unit-font-command	unit-font-command = $\langle command \rangle$ Command applied to text during output of units: should be command usable in math mode for font selection. Notice that in a typical unit this does not (necessarily) apply to all output, for example powers or brackets. The standard setting is <code>\mathrm</code> .

References

- [1] *The International System of Units (SI)*, <https://www.bipm.org/en/measurement-units/>.
- [2] *SI base units*, <https://www.bipm.org/en/measurement-units/si-base-units>.

Part X

siunitx-abbreviations – Abbreviations

`\A` Abbreviations for currents.
`\pA`
`\nA`
`\uA`
`\mA`
`\kA`

`\fg` Abbreviations for masses.
`\pg`
`\ng`
`\ug`
`\mg`
`\g`
`\kg`

`\K` Abbreviations for temperature.

`\m` Abbreviations for lengths.
`\pm`
`\nm`
`\um`
`\mm`
`\cm`
`\dm`
`\km`

`\s` Abbreviations for times.
`\as`
`\fs`
`\ps`
`\ns`
`\us`
`\ms`

`\Hz` Abbreviations for frequencies.
`\mHz`
`\kHz`
`\MHz`
`\GHz`
`\THz`

<code>\mol</code>	Abbreviations for moles.
<code>\fmol</code>	
<code>\pmol</code>	
<code>\nmol</code>	
<code>\umol</code>	
<code>\mmol</code>	
<code>\kmol</code>	

<code>\V</code>	Abbreviations for potentials.
<code>\pV</code>	
<code>\nV</code>	
<code>\uV</code>	
<code>\mV</code>	
<code>\kV</code>	

<code>\hl</code>	Abbreviations for volumes.
<code>\l</code>	
<code>\ml</code>	
<code>\ul</code>	
<code>\hL</code>	
<code>\L</code>	
<code>\mL</code>	
<code>\uL</code>	

<code>\W</code>	Abbreviations for powers.
<code>\nW</code>	
<code>\uW</code>	
<code>\mW</code>	
<code>\kW</code>	
<code>\MW</code>	
<code>\GW</code>	

<code>\kJ</code>	Abbreviations for energies.
<code>\J</code>	
<code>\mJ</code>	
<code>\uJ</code>	
<code>\eV</code>	
<code>\meV</code>	
<code>\keV</code>	
<code>\MeV</code>	
<code>\GeV</code>	
<code>\TeV</code>	

<code>\N</code>	Abbreviations for forces.
<code>\mN</code>	
<code>\kN</code>	
<code>\MN</code>	

<code>\Pa</code>	Abbreviations for pressures.
<code>\kPa</code>	
<code>\MPa</code>	
<code>\GPa</code>	

<code>\mohm</code>	Abbreviations for resistance.
<code>\kohm</code>	
<code>\Mohm</code>	

<code>\F</code>	Abbreviations for capacitance.
<code>\fF</code>	
<code>\pF</code>	
<code>\nF</code>	
<code>\uF</code>	

<code>\H</code>	Abbreviations for inductance.
<code>\fH</code>	
<code>\pH</code>	
<code>\nH</code>	
<code>\uH</code>	
<code>\mH</code>	

<code>\C</code>	Abbreviations for charge.
<code>\nC</code>	
<code>\uC</code>	
<code>\mC</code>	

<code>\dB</code>	Abbreviation for decibel.
------------------	---------------------------

<code>\kWh</code>	Abbreviation for kilowatt-hours.
-------------------	----------------------------------

Part XI

siunitx-binary – Binary units

This submodule provides binary units and prefixes. These are not formally part of the SI but are recommended by BIPM as units of information.

<code>\kibi</code>	Prefixes, all of which are integer powers of 2: the powers are <i>not</i> stored or available for conversion.
<code>\mebi</code>	
<code>\gibi</code>	
<code>\tebi</code>	
<code>\pebi</code>	
<code>\exbi</code>	
<code>\zebi</code>	
<code>\yobi</code>	

<code>\bit</code>	Units for bits and bytes.
<code>\byte</code>	

Part XII

siunitx-command – Units as document command

This submodule provides support for creating free-standing document commands for unit macros.

1 Creating units as document commands

\siunitx_command_create:

\siunitx_command_create:

Maps over the list of know unit commands and creates the appropriate document command to support them, as controlled by the options below.

1.1 Key-value options

The options defined by this submodule are available within the l3keys `siunitx` tree.

These options are all preamble-only.

free-standing-units

free-standing-units = true|false

Switch to determine whether free standing document commands are created for symbolic units. This will include not only units themselves but also prefixes, *etc.* The standard setting is **false**.

overwrite-commands

overwrite-commands = true|false

Switch to determine whether when creating free standing document commands, any existing document commands are overwritten. The standard setting is **false**.

space-before-unit

space-before-unit = true|false

Switch to determine whether a space is inserted before free standing document commands. The standard setting is **false**.

unit-optional-argument

unit-optional-argument = true|false

Switch to determine whether free standing document commands take an optional argument (a number). The standard setting is **false**.

use-xspace

use-xspace = true|false

Switch to determine whether free standing document commands use the `xparse` package to insert space after the command names. The standard setting is **false**. When set **true**, the `xparse` package will be loaded at the start of the document if not already available.

Part XIII

siunitx-emulation – Emulation

Index

The italic numbers denote the pages where the corresponding entry is described, numbers underlined point to the definition, all others indicate the places where it is used.

Symbols		D	
\,	9, 17, 21	\dalton	26
A		\day	26
\A	30	\dB	32
allow-quantity-breaks	17	\deca	25
\ampere	25	\deci	25
angle-mode	1	\decibel	26
angle-symbol-degree	1	\degree	26
angle-symbol-minute	1	\degreeCelsius	26
angle-symbol-over-decimal	1	\deka	25
angle-symbol-second	1	digit-group-first-size	9
arc-separator	1	digit-group-other-size	9
\arcminute	26	digit-group-size	9
\arcsecond	26	display-per-mode	28
\as	30	\dm	30
\astronomicalunit	26	drop-exponent	8
\atto	25	drop-uncertainty	8
B		drop-zero-decimal	8
\becquerel	26	E	
\bel	26	\electronvolt	26
\bfseries	13	\empty	6
\bit	33	\ensuremath	7, 13
\boldmath	14	\eV	31
bracket-ambiguous-numbers	8	evaluate-expression	9
bracket-negative-numbers	8	\exa	25
bracket-unit-denominator	27	\exbi	33
\byte	33	exponent-base	9
C		exponent-mode	9
\C	32	exponent-product	9
\cancel	21, 27	expression	9
\candela	25	extract-mass-in-kilograms	28
\centi	25	F	
\cm	30	\F	32
\color	6	\familydefault	13
color	14	\farad	26
compound-exponents	4	\femto	25
compound-final-separator	4	\fF	32
compound-pair-separator	4	\fg	30
compound-separator	4	\fH	32
compound-separator-mode	4	fill-angle-degrees	1
compound-units	4	fill-angle-minutes	1
\coulomb	26	fill-angle-seconds	2
\cubed	27	fixed-exponent	9
\cubic	26	\fmol	31
		\fontfamily	13
		\fontseries	13

<code>\fontshape</code>	13	<code>\joule</code>	26
<code>forbid-literal-units</code>	28		
fp commands:		K	
<code>\l_tmpa_fp</code>	22	<code>\K</code>	30
<code>\frac</code>	21	<code>\kA</code>	30
<code>fraction-command</code>	28	<code>\katal</code>	26
<code>free-standing-units</code>	34	<code>\kelvin</code>	25
<code>\fs</code>	30	<code>\keV</code>	31
		<code>\kg</code>	30
G		<code>\kHz</code>	30
<code>\g</code>	30	<code>\kibi</code>	33
<code>\ge</code>	6	<code>\kilo</code>	25
<code>\GeV</code>	31	<code>\kilogram</code>	25
<code>\gg</code>	6	<code>\kJ</code>	31
<code>\GHz</code>	30	<code>\km</code>	30
<code>\gibi</code>	33	<code>\kmol</code>	31
<code>\giga</code>	25	<code>\kN</code>	31
<code>\GPa</code>	32	<code>\kohm</code>	32
<code>\gram</code>	25	<code>\kPa</code>	32
<code>\gray</code>	26	<code>\kV</code>	31
group commands:		<code>\kW</code>	31
<code>\group_begin:</code>	24	<code>\kWh</code>	32
<code>\group_end:</code>	24		
<code>group-digits</code>	9	L	
<code>group-minimum-digits</code>	9	<code>\L</code>	31
<code>group-separator</code>	9	<code>\l</code>	31
<code>\GW</code>	31	<code>\le</code>	6
		<code>list-exponents</code>	4
H		<code>list-final-separator</code>	4
<code>\H</code>	32	<code>list-pair-separator</code>	4
<code>\hectare</code>	26	<code>list-separator</code>	4
<code>\hecto</code>	25	<code>list-units</code>	4
<code>\henry</code>	26	<code>\liter</code>	26
<code>\hertz</code>	26	<code>\litre</code>	26
<code>\highlight</code>	27	<code>\ll</code>	6
<code>\hL</code>	31	<code>locale</code>	5
<code>\hl</code>	31	<code>\lumen</code>	26
<code>\hour</code>	26	<code>\lux</code>	26
<code>\Hz</code>	30		
		M	
I		<code>\m</code>	30
<code>\ignorespaces</code>	19	<code>\mA</code>	30
<code>inline-per-mode</code>	28	<code>\mathchoice</code>	21
<code>input-close-uncertainty</code>	9	<code>\mathrm</code>	13, 21
<code>input-comparators</code>	9	<code>\mathversion</code>	13–15
<code>input-decimal-markers</code>	9	<code>\mbox</code>	13, 21
<code>input-digits</code>	10	<code>\mC</code>	32
<code>input-exponent-markers</code>	10	<code>\mdseries</code>	14
<code>input-open-uncertainty</code>	10	<code>\mebi</code>	33
<code>input-signs</code>	10	<code>\mega</code>	25
<code>input-uncertainty-signs</code>	10	<code>\meter</code>	25
<code>inter-unit-product</code>	28	<code>\metre</code>	25, 26
		<code>\MeV</code>	31
J		<code>\meV</code>	31
<code>\J</code>	31		

<code>\mg</code>	30	<code>\over</code>	29
<code>\mH</code>	32	<code>overwrite-commands</code>	34
<code>\MHz</code>	30		
<code>\mHz</code>	30	P	
<code>\micro</code>	25	<code>\Pa</code>	32
<code>\milli</code>	25	<code>\pA</code>	30
<code>minimum-decimal-digits</code>	10	<code>parse-numbers</code>	10
<code>minimum-integer-digits</code>	10	<code>parse-units</code>	28
<code>\minute</code>	26	<code>\pascal</code>	26
<code>\mJ</code>	31	<code>\pebi</code>	33
<code>\mL</code>	31	<code>\per</code>	27–29
<code>\ml</code>	31	<code>per-mode</code>	28
<code>\mm</code>	30	<code>per-symbol</code>	28
<code>\mmol</code>	31	<code>per-symbol-script-correction</code>	28
<code>\MN</code>	31	<code>\percent</code>	26
<code>\mN</code>	31	<code>\peta</code>	25
<code>mode</code>	14	<code>\pF</code>	32
<code>\Mohm</code>	32	<code>\pg</code>	30
<code>\mohm</code>	32	<code>\pH</code>	32
<code>\mol</code>	31	<code>\pico</code>	25
<code>\mole</code>	25	<code>\pm</code>	6, 12, 30
<code>\mp</code>	6	<code>\pmol</code>	31
<code>\MPa</code>	32	<code>\power</code>	27
<code>\ms</code>	30	<code>power-half-as-sqrt</code>	29
<code>\mV</code>	31	<code>prefix-mode</code>	17
<code>\MW</code>	31	<code>print-implicit-plus</code>	10
<code>\mW</code>	31	<code>print-unity-mantissa</code>	10
		<code>print-zero-exponent</code>	10
N		<code>print-zero-integer</code>	10
<code>\N</code>	31	<code>product-exponents</code>	4
<code>\nA</code>	30	<code>product-mode</code>	4
<code>\nano</code>	25	<code>product-phrase</code>	4
<code>\nC_U</code>	32	<code>product-symbol</code>	4
<code>negative-color</code>	10	<code>propagate-math-font</code>	14
<code>\neper</code>	26	<code>\ps</code>	30
<code>\newton</code>	26	<code>\pV</code>	31
<code>\nF</code>	32		
<code>\ng</code>	30	Q	
<code>\nH</code>	32	<code>qualifier-mode</code>	29
<code>\nm</code>	30	<code>qualifier-phrase</code>	29
<code>\nmol</code>	31	<code>quantity-product</code>	17
<code>\ns</code>	30		
<code>number-angle-product</code>	2	R	
<code>number-color</code>	14	<code>\radian</code>	26
<code>number-mode</code>	14	<code>\raiseto</code>	27
<code>\nV</code>	31	<code>range-exponents</code>	4
<code>\nW</code>	31	<code>range-phrase</code>	4
		<code>range-units</code>	4
O		<code>reset-math-version</code>	14
<code>\of</code>	27	<code>reset-text-family</code>	14
<code>\ohm</code>	26	<code>reset-text-series</code>	14
<code>output-close-uncertainty</code>	10	<code>reset-text-shape</code>	14
<code>output-decimal-marker</code>	10	<code>retain-explicit-decimal-marker</code>	11
<code>output-open-uncertainty</code>	10	<code>retain-explicit-plus</code>	10

retain-negative-zero	11	\siunitx_number_list:nn	3
retain-zero-uncertainty	11	\siunitx_number_normalize_-	
\rmfamily	14	symbols:N	8
round-half	11	\siunitx_number_output:N	7
round-minimum	11	\siunitx_number_output:n	7
round-mode	11	\siunitx_number_output:NN	6, 7
round-pad	11	\siunitx_number_output:nN	7
round-precision	11	\l_siunitx_number_output_-	
round-zero-positive	11	decimal_tl	8
		\siunitx_number_parse:nN	6, 7, 17, 19
		\l_siunitx_number_parse_bool ..	7, 8
		\siunitx_number_process:N	7
		\siunitx_number_process:NN	7
		\siunitx_number_product:n	3
		\siunitx_number_range:nn	3
		\l_siunitx_number_sign_tl	8
		\siunitx_prin_number:n	14
		\siunitx_print_...:n	13–15
		\siunitx_print_match:n	13
		\siunitx_print_math:n	13
		\siunitx_print_number:n	13
		\siunitx_print_text:n	13
		\siunitx_print_unit:n	13, 17
		\siunitx_quantity:nn	17
		\siunitx_quantity_list:nn	3
		\siunitx_quantity_print:nn	17
		\siunitx_quantity_product:nn	3
		\siunitx_quantity_range:nnn	3
		\l_siunitx_range_phrase_tl	4
		\l_siunitx_unit_font_tl	23
		\siunitx_unit_format:nN ..	17, 21, 22
		\siunitx_unit_format_combine_-	
		exponent:nnN	22
		\siunitx_unit_format_extract_-	
		prefixes:nnN	22
		\siunitx_unit_format_multiply:nnN	
		22
		\siunitx_unit_format_multiply_-	
		combine_exponent:nnnN	22
		\siunitx_unit_format_multiply_-	
		extract_prefixes:nnNN	22
		\l_siunitx_unit_fraction_tl	24
		\siunitx_unit_options_apply:n ..	23, 24
		\siunitx_unit_pdfstring_context:	24
		\l_siunitx_unit_seq	24
		\l_siunitx_unit_symbolic_seq ...	24
		space-before-unit	34
		\sqrt	29
		\square	26
		\squared	27
		\steradian	26
		sticky-per	29
		\symoperators	13
S			
\s	30		
\second	25, 26		
\selectfont	13		
separate-uncertainty-units	17		
series-version-mapping	16		
\seriesdefault	13		
\shapedefault	13		
\siemens	26		
\sievert	26		
siunitx commands:			
\siunitx_angle:n	1		
\siunitx_angle:nnn	1		
\l_siunitx_bracket_ambiguous_-			
bool	8		
\siunitx_cell_begin:w	19		
\siunitx_cell_end:	19		
\siunitx_command_create:	34		
\siunitx_compound_number:n	3		
\siunitx_compound_quantity:nn	3		
\siunitx_declare_power:NNn	23		
\siunitx_declare_prefix:Nn	23		
\siunitx_declare_prefix:Nnn	23		
\siunitx_declare_qualifier:Nn	23		
\siunitx_declare_unit:Nn	23		
\siunitx_declare_unit:Nnn ...	23, 24		
\siunitx_format_number:nN	1		
\siunitx_if_number:nTF	8		
\siunitx_if_number_p:n	8		
\siunitx_if_number_token:NTF	8		
\l_siunitx_list_separator_final_-			
tl	3		
\l_siunitx_list_separator_pair_-			
tl	3		
\l_siunitx_list_separator_tl	3		
\siunitx_number_adjust_exponent:Nn			
.....	7		
\siunitx_number_adjust_exponent:nn			
.....	7		
\l_siunitx_number_comparator_tl ..	8		
\l_siunitx_number_exponent_tl	8		
\siunitx_number_format:nN	7		
\l_siunitx_number_input_decimal_-			
tl	8		

T	
table-align-comparator	19
table-align-exponent	19
table-align-text-after	19
table-align-text-before	19
table-align-uncertainty	19
table-alignment	20
table-alignment-mode	20
table-auto-round	20
table-column-width	20
table-fixed-width	20
table-format	20
table-number-alignment	20
table-text-alignment	20
\tebi	33
\tera	25
\tesla	26
\TeV	31
\text	13
text-family-to-math	15
text-font-command	15
text-series-to-math	15
text-subscript-command	15
text-superscript-command	15
\textcenteredperiod	13
\textcolor	13–15, 21, 27
\textminus	13
\textpm	13
\textsubscript	13, 15
\textsuperscript	13, 15
\texttimes	13
\THz	30
tight-spacing	12
\times	6
tl commands:	
\l_tmpa_tl	21, 22
\tonne	26
\tothe	27
U	
\uA	30
\uF	32
\ug	30
\uH	32
\uJ	31
\uL	31
\ul	31
\um	30
\umol	31
uncertainty-descriptor-mode	12
uncertainty-descriptor-separator ...	12
uncertainty-descriptors	12
uncertainty-mode	12
uncertainty-separator	12
unit-color	15
unit-font-command	29
unit-mode	15
unit-optional-argument	34
\upshape	14
\us	30
use-xspace	34
\uV	31
\uW	31
V	
\V	31
\volt	26
W	
\W	31
\watt	26
\weber	26
Y	
\yobi	33
\yocto	25
\yotta	25
Z	
\zebi	33
\zepto	25
zero-decimal-as-symbol	12
zero-symbol	12
\zetta	25